


Beaded Weft Placement Guide

No heat, no glue, no braids - bead and wire installation.

- 1 Create the Section**
Part hair horizontally at nape, 1.5 inches above lowest hairline. Clip top up. Parted section should be thin and clean.
- 2 Thread Wire and Beads**
Cut extension wire to section width. Thread micro-ring beads onto wire, ~1cm apart. Need 8-12 beads per row.
- 3 Position the Wire**
Hold beaded wire against scalp along section line. Pull small sections of natural hair through each bead using loop tool. Wire sits flush.
- 4 Attach the Weft**
Position weft so fabric band sits inside beads, between wire and bead opening. Weft hangs as one continuous curtain below bead row.
- 5 Crimp the Beads**
Flat-jaw pliers crimp each bead flat from outside. Locks wire, natural hair, and weft band together. Check each bead by tugging.




For Textured & Natural Hair (3B-4C)

- No braiding required - ideal for all textures including 4A-4C
- No heat or adhesive means zero chemical damage
- Bead row sits completely flat against the scalp
- Wire can be adjusted without removing the weft

Aftercare, Maintenance & Troubleshooting

Spacing from Hairline



Care & Styling

Washing: Wash downward. Avoid scrubbing at bead row. Sulfate-free. Condition mid-lengths to ends.

Drying: Squeeze gently. Blow dry on low, away from bead row. Ensure beads dry fully.

Brushing: Hold bead row with one hand, brush below with other. Loop brush or wide-tooth comb.

Sleeping: Loose braid or silk scarf. Avoid sleeping on bead row.

Move-Ups: Every 8-12 weeks. Uncrimp, slide wire up, re-crimp. No new weft needed.

Troubleshooting

Issue	Solution
Weft dropping	Beads not crimped tight enough. Re-crimp each flat.
Bead row visible	Section too low or leave-out thin. Reposition higher.
Discomfort at beads	Sharp bead edge. Replace with new bead.
Wire poking	End not tucked. Bend into small loop and crimp.
Tangling at bead row	Brush more. Lightweight serum around beads daily.